



1



2

Iron interfacing on to the **WRONG** side of facing pieces and RST join the front and back neck facings at the shoulders. Press seams open and zigzag or overlock bottom edge of facings.

2



Sew a line of gathering stitches along sleeve head curve and pull threads to gather sleeve until it will fit the armhole.

3



Sew darts in on the wrong side of the dress front and press upwards.

4




RST join front and back bodices together at the shoulder seams.

5



Press seams open.

6



Apply interfacing to wrong side of what you will use as the bottom pieces of the left and right collar. Sew the bottom and top piece of the left collar RST, leaving a turning through gap as shown. Trim seam to 0.5cm, snip or notch around curved edges and turn through to right sides and press.